

Common Web Part Property Settings

Web Part properties		
Category	Property	Description
Appearance	Title	This property specifies the title of the Web Part appearing in the Web Part title bar.
	Height	This property specifies the height of the Web Part.
	Width	This property specifies the width of the Web Part.
	Chrome State	This property specifies if the entire Web Part should appear on the page when a user opens the Web Part Page. By default this property is set to Normal so that the entire Web Part appears. When this property is set to Minimized, only the title bar appears.
	Chrome Type	This property specifies if the title bar and border of the Web Part frame should be displayed.
Layout	Hidden	<p>This property specifies if the Web Part is visible when a user opens the Web Part Page. The web part is visible if the Layout check box is selected when designing a Web Part Page.</p> <p>If you want to provide data to another Web Part through a Web Part connection, you can hide the original Web Part.</p>
	Direction	This property specifies the direction of the text in the Web Part content. For example, English is written in a left-to-right direction. This setting may not be available for all types of Web Parts.
	Zone	<p>This property specifies the zone of a Web Part on a Web Part Page.</p> <p>NOTE: Zones on the Web Part Page are not listed in the list box when you do not have permission to modify the zone.</p>
	Zone Index	<p>This property specifies the position of the Web Part in a zone when the zone contains more than one Web Part.</p> <p>To specify the order of a Zone Index, you type a positive integer in the text box.</p> <p>If the Web Parts in the zone are ordered from top to bottom, a value of 1 means that the Web Part appears at the top of the zone. If the Web Parts in the zone are ordered from left to right, a value of 1 means that the Web Part appears on the left of the zone.</p>

Web Part properties

Category	Property	Description
		<p>NOTE: Each Web Part in the zone must have a unique Zone Index value. Changing the Zone Index value for the current Web Part can also change the Zone Index value for other Web Parts in the zone.</p>
Advanced	Allow Minimize	This property specifies whether the Web Part can be minimized.
	Allow Close	This property specifies whether the Web Part can be removed from the Web Part Page.
	Allow Hide	This property specifies whether the Web Part can be hidden.
	Allow Zone Change	This property specifies whether the Web Part can be moved to a different zone.
	Allow Connections	This property specifies whether the Web Part is available to connect and share data with other Web Parts.
	Allow Editing in Personal View	This property specifies whether the Web Part properties can be modified in a personal view.
	Export Mode	This property specifies the level of data permitted to be exported for a Web Part. Depending on your configuration, this setting may not be available.
	Title URL	This property specifies the URL of the file containing additional information about the Web Part. The file is displayed in a separate browser window when you click the Web Part title.
	Description	This property specifies the ScreenTip that appears when you rest the mouse pointer on the Web Part title or Web Part icon. This property value is also used by the Search command in the Find Web Parts menu of the tool pane for the Site, Virtual Server, and Web Part gallery of a Web Part Page.
	Help URL	This property specifies the location of a file containing Help information about the Web Part. The Help information is displayed in a separate browser window when you click the Help command on the Web Part menu.
	Help Mode	<p>This property specifies how a browser will display Help content for a Web Part. You can select one of the following:</p> <p>Modal: Opens a separate browser window, if the browser has this capability. A user must close the window before returning to the Web page.</p>

Web Part properties

Category	Property	Description
		<p>Modeless: Opens a separate browser window, if the browser has this capability. A user does not have to close the window before returning to the Web page. This is the default value.</p> <p>Navigate: Opens the Web page in the current browser window.</p> <p>NOTE: Microsoft Windows SharePoint Services 3.0 default help topics will only open in a separate browser.</p>
	Catalog Icon Image URL	This property specifies the location of an image file to be used as the Web Part icon in the Web Part List. The image size must be 16 x 16 pixels.
	Title Icon Image URL	This property specifies the location of an image file to be used in the Web Part title bar. The image size must be 16 x 16 pixels.
	Import Error Message	This property specifies a message that appears if there is a problem importing the Web Part.